


ErosPulse

Feature tour, with application previews

v0.16.0

Home page



1. Overview

ErosPulse transforms a sequence of commands into real vibrations on a Lovense Edge 2, motor by motor, live. The application consists of three screens: Home, Toy Connection, and the Sequence screen where everything takes place.

- Local connection to the toy via the Lovense Remote app (Game Mode), without an account or cloud.
- Independent control of both Edge 2 motors (internal / perineal).
- A compact and readable command format: `[Y;D;[A;B]]`, with loops (LOOP).
- Live playback with pause/resume, intensity graph, countdown timer.
- Import ready-to-use sequences from a folder of .txt files.
- 100% standalone application: all dependencies are embedded.


2. Home page

The entry point of the application. It displays the connection status in real time and offers a direct path to the next action, without unnecessary steps.

Home page preview

Smart navigation

The Start button does not always lead to the same place: if no toy is connected, it opens the connection page; if a toy is already connected, it goes directly to the sequence page. No unnecessary detour once the connection is established.



3. Toy Connection

The connection is done entirely locally, via "Game Mode" in the Lovense Remote mobile app: no registration, no remote server.

Connection page preview

Motor testing

Two dedicated buttons allow testing each Edge 2 motor independently — practical for confirming which is which before launching a real sequence. Each button automatically connects if needed, then sends a short vibration to the concerned motor only.

Connection saved by the session

Once connected, the connection status remains active as long as the application is running: no need to reconnect with each page change.

[<- Accueil](#)

Etapas dans l'app Lovense Remote (telephone)

1. Verifie que l'Edge 2 est bien appaire (Bluetooth) a l'app.
2. Onglet Discover -> Game Mode.
3. Active <<LAN>>.
4. Note l'IP locale et le port affiches, et saisis-les ci-dessous.
5. Le telephone et cet ordinateur doivent etre sur le meme Wi-Fi.

IP locale

192.168.1.42

Port

30010

☒ Utiliser HTTPS

Se connecter

Tester Moteur 1 (interne)

Tester Moteur 2 (perinee)

Connecte OK -- toy detecte : Edge 2

Continuer ->

4. Sequence page

The heart of the application. This is where the vibration sequence is written, imported, previewed, and played on the connected toy.

Sequence page preview, during playback

The [Y;D;[A;B]] format

Each command specifies which motor to activate, for how long, and at what intensity:

```
[Y;D;[A;B]]
```

- Y : 1 = internal motor, 2 = perineal motor, 3 = both together
- D : duration in seconds
- A / B : intensity of each motor, from 0 to 20

A repeating pattern can be written just once using LOOP:

```
LOOP(3){[1;2;[10;0]] [2;2;[0;15]]}
```

Preset import

[<- Accueil](#)Edge 2 connecte

Colle ici une sequence au format [Y;D;[A;B]] (Y=moteur, D=duree, [A;B]=intensites). Repete un bloc avec LOOP(N){ ... }.

[Modeles: Exemple - vague](#)[Rafraichir](#)[Dossier...](#)[Masquer le texte](#)[.../ErosPulse/Import](#)

```
LOOP(3){[1;2;[10;0]] [2;2;[0;15]] [3;3;[18;20]]}
```

Moteur 1

Moteur 2

Temps restant : 0:0848 / 4000 caracteres

[Generer le modele de vibration ->](#)[Pause](#)

Commande 3/7 -- [1;2;[10;0]]

A dropdown menu lists ready-to-use sequences (.txt files) present in a configurable folder. Selecting a template instantly loads its content into the editor, ready to be adjusted or launched as is.

Live intensity graph

One curve per motor visually shows the progression of the sequence even before launching it. During playback, a vertical marker tracks progress in real time.

True pause, not a simple stop

Pausing immediately cuts off vibration. Upon resuming, the current command picks up for the exact remaining time — never from the beginning. Navigating away from the page during playback automatically pauses rather than interrupting: returning to the page allows you to resume where you left off.

5. What makes the app standalone

- Zero external dependencies to install: the vendor/ folder embeds everything needed (requests, urllib3...). A simple python main.py is enough.
- Standalone executable: ErosPulse.spec + build_exe.bat/.sh generate a program ready for distribution, with no need to install Python on the target machine.
- Persistent settings: the selected presets folder is remembered from one launch to another.
- AI Prompt provided: a ready-to-use prompt (core/ai_prompt.py) allows an AI to generate a [Y;D:[A;B]] sequence from plain text.